

Getting Started – Configuring Your Computer Network Settings

Mitchell Telecom uses the following for their mail server setup:

Server Type: **POP3**

Incoming Mail Server: **pop.mitchelltelecom.net**

Outgoing Mail Server: **mail.mitchelltelecom.net**

How to Set Up Windows Live Mail for Vista and Windows 7


Start Windows Live Mail

There are many ways to start Windows Live Mail, but here's a sure-fire way to find and start it.


1. Click the **Start** button.
2. Point to **All Programs**.
3. Click **Windows Live** and then click **Windows Live Mail**.

Set Up an Windows Live E-Mail Account in Windows Vista Operating System


4. On the **Tools** menu, click **E-mail Accounts**.



5. Select **Add a new e-mail account**



6. Select **POP3** e-mail server used for your account, and then click **Next**.



7. In the appropriate boxes, type the information given to you by Mitchell Telecom.

- Your Name
- Your E-mail Address
- The name of the incoming e-mail server: **pop.mitchelltelecom.net**
- The name of the outgoing e-mail server: **mail.mitchelltelecom.net**
- Your User Name
- Your Password

Notes:

You have the option of having Windows Live remember your password by typing it in the **Password** box and selecting the **Remember password** check box. While this means that you won't have to type in your password each time you access the account, it also means that the account is vulnerable to anyone who has access to your computer.

9. Click **Next**.
10. Click **Finish**.

Set Up an Windows Live E-Mail Account in Windows 7 Operating System

Start Windows Live Mail

There are many ways to start Windows Live Mail, but here's a sure-fire way to find and start it.

1. Click the **Start** button.
2. Point to **All Programs**.
3. Click **Windows Live** and then click **Windows Live Mail**.
4. Click add email account on the Left Side of the Screen and the following window should appear

Add an E-mail Account

Please enter your e-mail account information below:

E-mail address: [Get a free e-mail account](#)

Password:

Remember password

How should your name appear in e-mail sent from this account?

Display Name:

For example: John Smith

Manually configure server settings for e-mail account.

Next Cancel

6. In the appropriate boxes, type the information given to you by Mitchell Telecom.
 - Your E-mail Address
 - Your Password
 - Your Name
7. Click **Manually Configure server settings for email account** and click **Next**

Where can I find my e-mail server information?

Incoming Server Information

My incoming mail server is a **POP3** server.

Incoming server: Port:

This server requires a secure connection (SSL)

Log on using: **Clear text authentication**

Login ID (if different from e-mail address):

Outgoing Server Information

Outgoing server: Port:

This server requires a secure connection (SSL)

My outgoing server requires authentication

8. Enter the following information in the **Incoming Server** and **Outgoing Server** Fields
 - The name of the incoming e-mail server: **pop.mitchelltelecom.net**
 - The name of the outgoing e-mail server: **mail.mitchelltelecom.net**
9. Click **Next** and **Finish**